

Title:

RC3600 DATAENTRY RELEASE 2

USER'S GUIDE FOR SUPERVISORPROGRAM REESTABLISH

 **REGNECENTRALEN**

RC SYSTEM LIBRARY: FALKONERALLE 1 DK-2000 COPENHAGEN F

RCSL No: 43-GL5853

Edition: JANUARY 1978

Author: Flemming Havmøller

Keywords:

MUS, DOMUS, DATA ENTRY, SUPERVISORPROGRAM, RESTABLISH

Abstract:

This manual describes how to use the supervisor program RESTABLISH.

The program changes a field in the Batchhead(s) without using the protection system.

CONTENTS

PAGE

-
1. INTRODUCTION 1
 2. PROGRAM: RESTABLISH - change the contents of batchheads 2

1. INTRODUCTION.

1.-

This manual describes how to use the supervisor program RESTABLISH.

For further description of the program see the following pages, page 2 and 3.

These two pages (page 86 and 87) can be inserted in the:

RC3600 DATA ENTRY RELEASE 2

USERS GUIDE PART 2

RCSL: 43-GL4796

EDITION: JUNE 1977

instead of the already existing 2 pages.

The reason for this manual is some changes in the program as described below.

Batch statusword is extended with one word, this word (word 2) can be changed by the Fieldname STAT2 and the old Batch statusword (word 1) can still be changed by the Fieldname STATU or by the new Fieldname STAT1.

It is now possible to change not used words in the Batch-head by using the Fieldname WD followed by the no. of the word, which is to be changed.

This wordno. must be inside the limits of 28 and 255.

2. PROGRAM: RESTABLISH - change the contents of batchheads.

2.

- KEYING:
1. Key: RESTABLISH
 2. If a single batchhead should be changed
Key: BATCH
If the batchheads of all batches in a job should be changed
Key: JOB
 3. Key: .
 4. Key: Name of batch or job
 5. If a specified field in the bathhhead of a specified batch should be changed.
Key: Name of field (see below) and
Key: . and
Key: New contents of field (see below)

Field	Name of field	Type of new contents of field
JOBNAME	JOBNA	STRING OF 5 CHARACTERS
FORMATNAME	FORMA	STRING OF 5 CHARACTERS
BATCH STATUS 1	STATU STAT1	INTEGER or INTEGER
BATCH STATUS 2	STAT2	INTEGER
BYTECOUNT OLD BATCH	SBYTE	INTEGER
BYTECOUNT NEW BATCH	NBYTE	INTEGER
BLOCK ADDRESS CHECKPOINT	BLADD	INTEGER
BYTE ADDRESS CHECKPOINT	BYADD	INTEGER
NO OF BLOCKS	BLOKS	INTEGER
NO OF RECORDS	RECOR	INTEGER
NO OF REKEYED RECORDS	REKEY	INTEGER
NO OF INVALID. RECORDS	INVAL	INTEGER
DAY NUMBER	DAYNU	INTEGER
SECOND NUMBER	SECON	INTEGER
BLOCK NO OLD BATCH	SBLOC	INTEGER
BLOCK NO NEW BATCH	NBLOC	INTEGER
SUBNAME	SUBFO	STRING OF 1 CHARACTER
CURR. RECORDNO OLD	ORECN	INTEGER
CURR. RECORDNO NEW	NRECN	INTEGER
MAX. RECORDNO NEW	MRECN	INTEGER
END FORMAT	ENDFO	INTEGER
UNUSED WORDS	WD<NO>	INTEGER
FIRST WORD = 28	WHERE<NO> IS WORD NO.	
LAST WORD = 255		

6. Press the ENTER key.

DESCRIPTION: This program changes a field in the batchhead(s) without using the protection system. 2.

If the program is activated with a specified field name (allowed in connection with a single batch, only), the field will be changed to the specified contents.

Activation without fieldname specification (on a single batch or on all batches in a job) NBLOC.0 is understood; i.e. 'block number in new batch' is set to zero.

Notice:

The use of the program is of the supervising operator's own responsibility because it can make irreparable damage to the batches involved.

EXAMPLES:

- 1) REESTABLISH BATCH.B0005
- 2) REESTABLISH JOB.J0001
- 3) REESTABLISH BATCH.B0005 NBLOC.0 - equivalates 1)
- 4) REESTABLISH BATCH.BAT3 STATUS.0
- 5) REESTABLISH BATCH.BAT3 WD58.0

RECEIPTS:

NOT NAME	The specified name is not a discfile
IDENT UNKNOWN	The specified name (ident) is not a job
NAME UNKNOWN	The specified field name is not known
NAME SYNTAX	The type of new contents is illegal
NOT BATCH	The specified name is not a batch
BATCH OK <Number>	The program execution has terminated successfully. <Number> is the octal number of batches changed.
DISC ERROR <Code>	Consult appendix 2.