



Text Editor

Version Two



36000



Text Editor

Version Two

A/S REGNECENTRALEN
Documentation Department

Revision 2
February 1976
RCSL No. 42 - i 0337

Author: Joan Rosenstein
Technical Editor: Claus Anton Sørensen
Text Editor: Claus Terp

KEY WORDS: Editing, de-bugging, program coding.

ABSTRACT: This manual describes the use of a text editor for creating, modifying, up-dating, and de-bugging MUSIL source code.

Users of this manual are cautioned that the specifications contained herein are subject to change by RC at any time without prior notice. RC is not responsible for typographical or arithmetic errors which may appear in this manual and shall not be responsible for any damages caused by reliance on any of the materials presented.

Copyright © A/S Regnecentralen, 1976
Printed by A/S Regnecentralen, Copenhagen

Table of Contents

1	INTRODUCTION	page	5
	1.1 Overview		5
	1.2 The Logic of Text Editor		6
	1.3 The Use of Special Keys		7
	1.4 Parity Errors		8
2	THE EDITING PROCEDURE		9
	2.1 Beginning the Editing Procedure		9
	2.2 Device Handling		9
	2.3 Conversion Table Programs		11
	2.4 Device Errors		12
	2.5 Input Commands		12
	2.6 Commands to the Character Pointer		13
	2.6.1 Example of Commands to the CP		15
	2.7 Text Modification Commands		16
	2.7.1 Example of Text Modification Commands		19
	2.8 The Macro Command		20
	2.8.1 Example of Macro Commands		21
	2.9 Output Commands		22
	2.10 Special Commands		23
3	ERROR MESSAGES		25
4	REFERENCE LIST OF MUSIL TEXT EDITOR COMMANDS		26
APPENDIX:			
DISC CARTRIDGE EDITOR SYSTEM			
	Initialization		A 1
	For Similar Input and Output Filenames		A 2
	Example of Disc Cartridge Text Editor Commands		A 3
	Disc Cartridge Error Messages		A 3

1 Introduction

1.1 Overview

The MUSIL Text Editor can be used to modify, update, or create MUSIL programs while sitting at the operator's console of the RC 3600. The editing procedure can be carried out on individual characters, on strings of characters, or on program segments.

The handiest device to use with Text Editor is an alphanumeric display with a keyboard, because such devices are fast and quiet, and deletions and changes are easiest to observe when using these devices, but the F 12 KSR Teletype is also preferred by many because of the permanent record it gives of the editing process. The F 14 Silent Printer/Keyboard combines quiet operation with a permanent record.

Text Editor allows you to edit MUSIL programs with input from the card reader, paper tape reader, magnetic tape unit, flexible or cartridge disc, or cassette tape unit and output to the paper tape punch, magnetic tape unit, cassette tape unit, line printer, serial printer or flexible or cartridge disc.

Text Editor can modify a program text either at the line or the character level. It does this by searching either for a string of characters or for an implicit line number. Text Editor provides these implicit line numbers, and also an implicit character pointer to the current characters.

There are three types of Text Editor commands: input commands that put the user program - or a part of the user program - into the edit buffer, commands that modify the contents of the edit buffer, and commands that output the modified contents of the edit buffer.

At each point of the editing procedure there is a character pointer (CP) that points to the position that currently is available for operating on.

Each line that is read into the edit buffer is assigned an implicit sequential line number, beginning with 1, that is updated as the editing procedure progresses. Text Editor defines a line as text ending with a carriage return. When

the user requests a line number, Text Editor calculates the line number by counting carriage returns from the beginning of the buffer.

All text is assumed to be in ASCII, and in the parity that is normal for the hardware used (see the MUSIL Programmer's Reference Manual). That is, Text Editor assumes that all input to it is in ASCII, and outputs in ASCII also. For input and output that is not in ASCII, a conversion table program must be loaded along with the Text Editor program. Such programs are written in MUSIL and can be generated by the programmer or obtained from Regnecentralen.

1.2 The Logic of Text Editor

Text Editor views all input to it as a continuous stream of ASCII characters. This stream of characters is considered to be segmented into pages. A "page" is defined as a stream of characters up to a form feed character or to the end of input. Each page is segmented into lines. A "line" is defined as a stream of characters up to and including a carriage return.

In theory a page may be up to 4750 characters in length, but in practice no page may be this long, for within the 4750 characters there must be room for the Text Editor commands.

The editing process takes place in three steps:

1. read a page into the edit buffer,
2. edit this page,
3. output this page, as modified.

When Text Editor has been loaded, it prints an * (asterisk), and the user may begin editing. If at any point the capacity of the edit buffer is exceeded, then the appropriate error message will be printed.

The character pointer (CP) should be thought of as placed between two characters. Inserted characters will be placed between these characters. Operations on the current character will occur on the character to the right of the CP.

1.3 The Use of Special Keys

The Escape Key, ESC, is used for two purposes:

1. Striking ESC twice initiates processing of the command(s) just typed.
2. Striking ESC once after the argument to a command code delimits that argument from whatever may be typed after it.

When ESC is struck, a \$ (dollar sign) is displayed.

Each command consists of one or two letters or a special graphic. This is the "command code". Some commands allow you to place a number in front of them. These numbers must be decimal integers between zero and ± 2047 . Some command codes may be followed by a string argument.

Each command has the form:

`n code string $`

where \$ represents the ESC key, and n and/or string may be absent, depending on the specific case.

To initiate processing of this command, the ESC key is pressed once more, if the command ends with a dollar sign, or twice if it does not.

Several commands may be written one after the other before processing is initiated. In this case we have a string of commands, such as

`n code string$n code string$ $`

To execute this command string, the ESC key must be struck once more. Remember that processing begins upon the reception of a sequence of two ESCs. An accidental third ESC will have no ill effects.

Carriage return, CR, will have no effect if struck within a command string, as long as it is struck only between commands, and not in the middle of a command. If CR is struck within a string of characters, then Text Editor will assume that CR is part of this string.

RUBOUT is used to delete the last character input. On a teletype it is represented by a back arrow. See the Operator's Guide for its effect on other

devices. Repeated RUBOUTs delete as many characters as there are RUBOUTs, from right to left, until a "terminator" is reached. A "terminator" is any character whose ASCII code is below decimal 32, such as ESC, new line, tabulation, form feed, etc. In practice the deletion process usually goes to the CR that signals the end of the preceding line. Example:

```
start : FIRSTTT↑
action : two RUBOUTs
result : FIRST↑
```

The up arrows indicate the position of the CP.

RUBOUT cannot delete terminators, but pressing the CTRL key together with H will cause the last character input to be deleted whether or not it is a terminator. The deleted character will be echoed on the console.

Tabs are simulated with spaces, that is, they appear as spaces on the operator device. On the output they appear as the TAB character followed by the RUBOUT character. Predefined TAB positions occur at columns 1, 9, 17, 25, etc. TAB positions cannot be redefined by the user. (See the Insert command for the method used to insert tabs.)

NULL and LINE FEED will be ignored on input, but a line feed will be provided for every CR sent to the output device.

When the CTRL, Control Key, is pressed together with a character, then the ASCII sum of the combination is input.

1.4 Parity Errors

Parity is always checked on input from paper tape, where even parity is assumed. If an input character contains a parity error, then the following message will be delivered:

```
PARITY ERROR IN LINE n
```

If the user then examines that line, the character in error will appear as a /.

The occurrence of a parity error will cause the execution of some commands to come to a halt. These commands are

```
E, N, H, R, Q
```

2 The Editing Procedure

2.1 Beginning the Editing Procedure

Before editing can take place the machine must of course be in operation and the necessary programs will have to be loaded. Consult the Operator's Guide for loading procedures.

Specifically, before beginning editing

The basic system must be autoloaded,
 All necessary driver programs must be loaded,
 The MUSIL interpreter must be loaded,
 Text Editor must be loaded,
 Conversion table programs, if needed, must be loaded, and
 The source text (if any) must be ready for input.

After program loading Text Editor takes command, clears its buffers, and is in control. This is indicated by the printing of an *.

2.2 Device Handling

When loading has been accomplished and Text Editor has assumed control, the initial asterisk delivered, and the user is ready to begin, Text Editor must be told which physical device to use.

GR inputfilename\$ get for reading

will open the file with the specified name, after first closing a currently open input file, if any. If the file does not exist, then the message

NO SUCH FILE

will be displayed.

GW outputfilename\$ get for writing

will open an output file with name specified. If the file does not exist, then

NO SUCH FILE

will appear.

For files that, like magnetic tape, have set position possibilities, write

GR inputfilename:xx\$\$

or GW outputfilename:xx\$\$

where xx is the file number. For example:

GR\$MT0 :1\$

GW\$MT1:1\$\$

The input and output filenames available with Text Editor are:

Paper tape reader	\$PTR
Paper tape punch	\$PTP
Line printer	\$LPT
Serial printer	\$SP
Card reader	\$CDR
Magnetic tape unit 0	\$MT0
Magnetic tape unit 1	\$MT1
Magnetic tape unit 2	\$MT2
Magnetic tape unit 3	\$MT3
Cassette tape unit 0	\$CT0
Cassette tape unit 1	\$CT1
Flexible disc unit 0	\$FD0
Flexible disc unit 1	\$FD1

where the \$ is a true dollar sign, and NOT the escape key.

These devices restrict the use of GR and GW in that these commands cannot both be used on the same device. That is, if one has written, for example,

GR\$MT0:1\$\$

then one cannot subsequently write

GW\$MT0:2\$\$

The reason for this is that the peripheral device's driver program can perform only reading or writing, but not both.

Disc cartridge I/O is also available with Text Editor, but because the disc cartridge is handled somewhat differently than the other devices, its use is explained in the Appendix.

For the flexible disc, initialization must precede the "get" commands. This is accomplished by the command

```
GI$FDn$           get diskette initialization and erase
```

where $n = 0$ or 1 . This command will create a new catalog in track zero and erase previous data in that track.

To append multiple input files to produce a single output file, use the GR command for each input file, but declare only one output file. Remember that GR will close the current input file before opening a new one.

2.3 Conversion Table Programs

A conversion table program written in MUSIL must be loaded along with the Text Editor program for any non-ASCII device that will be used for input to, or output from, Text Editor. This situation will occur with card readers using EBCDIC and printers using non-ASCII print drums. Conversion table programs have the form (as ordinary MUSIL programs):

```
CONST
      TABLE = #..... !CONVERSION TABLE!
              .....
              ..... #;
BEGIN
END;
```

Conversion tables for the devices specified may be obtained from Regnecentralen.

During compilation of the conversion table program the program must be given the name

```
CITAB   if referring to a card reader
CLTAB   if referring to a line printer
```

2.4 Device Errors

If a device error occurs, the message

```
devicename ERROR errornumber
CORRECT ERROR WRITE START/STOP
```

will be displayed.

To correct the error, consult the Operator's Guide for the error number. After making the correction, press RETURN. The operation at which the error occurred will repeat itself automatically.

If you cannot correct the error, write STOP and press RETURN. The program will then ignore the command that gave rise to the error and will prompt for a new command.

For example, you have put in

```
GW$LPT$$
```

and

```
LPT ERROR 21
CORRECT ERROR WRITE START/STOP
```

appears. This means that the line printer is off-line. To correct the situation, put the line printer on-line and press RETURN. Text Editor will now automatically execute

```
GW$LPT$$
```

2.5 Input Commands

```
Y          read a page
```

The next page of the user program is read into the edit buffer. The form feed at the end of the page will be read, but not stored in the edit buffer. The CP will be positioned to just before the first character in the edit buffer. If the edit buffer is exceeded, the following message will be printed:

```
BUFFER IS FULL - Y OR A INPUT IS TERMINATED
```

If this message is received, then a part of the current page is in the edit buffer. To continue the editing process, the user must either read out the buffer

or delete something from it. The rest of the page can then be read in by means of the A command.

When the text is to be input from the console device, then the Insert command is used instead of the Y command.

A append a page

The next page is added to the present contents of the edit buffer. The CP will be positioned just before the first character of this new page. If the buffer is full before the command is given, or if it fills up while the command is being executed, then

BUFFER IS FULL - Y OR A INPUT IS TERMINATED

will appear.

T display contents of edit buffer on console device

The CP is not affected. The entire contents of the edit buffer will appear on the display device.

nT display n lines of edit buffer

will display n lines of the edit buffer, starting from the current position of the CP, and CP will not be moved.

2.6 Commands to the Character Pointer

B place CP at beginning of edit buffer

The CP is moved to just before the first character in the edit buffer. If an argument is used with this command, then the argument will be ignored.

nJ jump CP to line n

The CP will be moved to just before the first character of the n-th line of the edit buffer.

L move CP to beginning of line

Moves the CP to before the first character of the current line.

nL move CP n lines

The CP will move n lines from its current position and then place itself just before the first character of the new line:

for $n > 0$, move forward past n carriage returns

for $n < 0$, move backwards past $|n| + 1$ carriage returns and forward one character

for $n = 0$, place CP to just before the first character of the current line (equivalent to L)

If n is so large that it is attempted to move the CP past the limits of the edit buffer contents, then the command will result in the CP being placed after the last character of the buffer (if n is positive), or before the first character of the buffer (if n is negative).

nM move CP n characters

This moves the CP with respect to individual characters.

for $n > 0$, CP is moved n character positions forward

for $n < 0$, CP is moved $|n|$ character positions backwards

for $n = 0$, there is no effect on CP

Note that a tab is one single character in the internal data representation.

Z move CP to end of edit buffer

CP ends up just after the last character of the edit buffer.

2.6.1 Example of Commands to the CP

- Δ represents a blank space
 (n) represents the implicit line number
 ← represents carriage return

In the edit buffer originally is

```
(1)TABLEΔ=Δ#25Δ56Δ43←(2)54Δ97Δ56←(3)00Δ55Δ97←
      ↑CP
```

Subsequently:

Command	Result
B\$\$	(1)TABLEΔ=Δ#25Δ56Δ43←(2)54Δ97Δ56←(3)00Δ55Δ97← ↑CP
3J\$\$	(1)TABLEΔ=Δ#25Δ56Δ43←(2)54Δ97Δ56←(3)00Δ55Δ97← ↑CP
-1L\$\$	(1)TABLEΔ=Δ#25Δ56Δ43←(2)54Δ97Δ56←(3)00Δ55Δ97← ↑CP
Z\$\$	(1)TABLEΔ=Δ#25Δ56Δ43←(2)54Δ97Δ56←(3)00Δ55Δ97← ↑CP
-15M\$\$	(1)TABLEΔ=Δ#25Δ56Δ43←(2)54Δ97Δ56←(3)00Δ55Δ97← ↑CP
L\$\$	(1)TABLEΔ=Δ#25Δ56Δ43←(2)54Δ97Δ56←(3)00Δ55Δ97← ↑CP
2J\$\$	(1)TABLEΔ=Δ#25Δ56Δ43←(2)54Δ97Δ56←(3)00Δ55Δ97← ↑CP
50M\$\$	(1)TABLEΔ=Δ#25Δ56Δ43←(2)54Δ97Δ56←(3)00Δ55Δ97← ↑CP

The same effect can be obtained by writing the commands as a single command string, thus:

```
B$3J$ - 1L$Z$ - 15M$L$2J$50M$$
```

2.7 Text Modification Commands

These commands often contain arguments (operands). Each argument is delimited by \$. Thus, commands with arguments end with one \$, as shown below, and to initiate execution only one more \$ is needed, for a sum of \$\$.

Cstring₁\$string₂\$ search for and replace string

will cause Text Editor to search forward (only) from the current position of the CP for (only) the first occurrence of string₁ and replace it with string₂. If the end of the edit buffer is reached before the string is found, then

STR NOT FOUND

will be displayed and the CP will be placed before the first character of the edit buffer, allowing the user to search the rest of the buffer for the string by repeating the command. If the string is found, then the CP is placed just after the last character of string₂.

To simply delete a string, the C command can be used with an empty string₂, that is, we type

Cstring\$\$ delete string

The CP will be placed at the point of the deletion. The two terminators are necessary to indicate that the second string is empty.

Istring\$ insert string

The string is inserted at the current position of the CP. The CP is then moved to just after the inserted string.

The Insert command can be used to insert tab and form feed characters in the text. The tab character is represented by CTRL I, written

↑I

and the form feed character is represented by CTRL L, written

↑L

That is, one may write commands such as

I ↑I \$ or I ↑L \$

STR NOT FOUND

is displayed and CP will be placed just before the first character of the edit buffer, enabling the rest of the buffer to be searched by a repetition of the command.

Qstring\$ search for string through input

The Editor searches forward from the current position of the CP for the first occurrence of the string and positions CP to just after this first occurrence. If the end of the edit buffer is reached before the string is found, then the search will be conducted through the remaining input. Searched pages before the one containing the string sought are not retained as output. If the string is not found,

STR NOT FOUND

will be displayed.

Nstring\$ search, output, and read

This command causes Text Editor to search forward in the edit buffer from the current position of the CP for the string. If the end of the buffer is reached before the string is found, then Text Editor reads in the next page of the input until the buffer is filled again, having output the first buffer contents. This process continues until the first occurrence of the string is found. If the end of the input is reached before then,

STR NOT FOUND

is displayed. The CP is placed just before an empty edit buffer, and all input is transferred to the output file.

The N command can be used for copying magnetic or cassette tapes. It will stop execution only when the string is found or a double filemark is encountered. Single filemarks will, moreover, be copied. If the string to be searched for is given in such a way that it does not exist on the tape, then N can be used to copy the tape, including its single filemarks.

Tapes copied in such a way will not have double filemarks on them. These must be put in by the execution of a GC command, described in the section on Output Commands.

2.7.1 Example of Text Modification Commands

- Δ represents a blank
 (n) represents the implicit line number
 ← represents a carriage return

In the edit buffer originally is

```
(1)BEG IN←(2)ΔΔΔΔ IFΔ IN. ZMODE = 0Δ THENΔ OPEN(IN, 1);←
  ↑CP
```

Subsequently:

Command	Result
CTHEM\$THEN\$\$	(1)BEG IN←(2)ΔΔΔΔ IFΔ IN. ZMODE=0Δ THENΔ OPEN(IN, 1);← ↑CP
CIN, 1\$\$	(1)BEG IN←(2)ΔΔΔΔ IFΔ IN. ZMODE=0Δ THENΔ OPEN();← ↑CP
IINN. 1\$\$	(1)BEG IN←(2)ΔΔΔΔ IFΔ IN. ZMODE=0Δ THENΔ OPEN(INN. 1);← ↑CP
-3M\$\$	(1)BEG IN←(2)ΔΔΔΔ IFΔ IN. ZMODE=0Δ THENΔ OPEN(INN. 1);← ↑CP
3D\$\$	(1)BEG IN←(2)ΔΔΔΔ IFΔ IN. ZMODE=0Δ THENΔ OPEN(IN);← ↑CP
B2M\$\$	(1)BEG IN←(2)ΔΔΔΔ IFΔ IN. ZMODE=0Δ THENΔ OPEN(IN);← ↑CP
1K\$\$	(1)BEΔΔΔΔ IFΔ IN. ZMODE=0Δ THENΔ OPEN(IN);← ↑CP
0K\$\$	(1)ΔΔΔΔ IFΔ IN. ZMODE=0Δ THENΔ OPEN(IN);← ↑CP
2M\$\$	(1)ΔΔΔΔ IFΔ IN. ZMODE=0Δ THENΔ OPEN(IN);← ↑CP
-1K\$\$	(1)ΔΔ IFΔ IN. ZMODE=0Δ THENΔ OPEN(IN);← ↑CP
IBEGIN\$\$	(1)BEG INΔΔ IFΔ IN. ZMODE=0Δ THENΔ OPEN(IN);← ↑CP

2.8 The Macro Command

Text Editor provides for the definition and execution of a macro command. A macro command is defined as a single command which contains an arbitrary command string. Once defined, the macro command is retained by Text Editor for future execution by means of a single symbol. Text Editor allows for the definition of only one macro at a time.

To specify the contents of a macro command, issue the command

```
XMcommand1command2 ..... commandn    create macro
```

where "command" has the format

```
n code string$
```

The command

```
X$$    execute macro
```

will cause the macro to be executed as defined.

```
nX$    execute macro n times
```

will cause the macro to be executed a number of times in succession. Note that

```
X$$, 0X$$, 1X$$
```

are all equivalent, and will cause the macro to be executed once.

A defined macro may be deleted at any time by issuing the command

```
XD$    delete macro
```

If a macro is recursive in execution, then the message

```
MACRO CONTAINS X IN COMMAND
```

will be displayed.

If the macro is not properly defined, then the message will be

```
MACRO UNDEFINED
```

```
??
```

```
the command in error
```


2.9 Output Commands

F form feed

This command outputs a form feed character to the output file, along with 10 zeroes before and after the form feed character. These zeroes will be ignored when the file is later read. When the output file is later read, and if it is to be used with a printer, then the occurrence of the form feed character will cause the printer to begin a new page.

nF n inches of leader output

The Editor will output n inches of leader, up to 100 inches. If n is greater than 100, then 100 inches will be output. In the case of paper tape this means that n inches of blank tape will be punched. OF\$\$\$ causes the same effect as F\$\$\$. Neither the F nor the nF command has any effect on the CP.

P output buffer

The entire edit buffer is output, followed by a form feed preceded and followed by ten zeroes. The CP and the edit buffer remain unchanged.

nP output n lines

Starting from the CP, n lines are output, plus a form feed, as above. If the end of the text in the buffer is reached before n lines are output, then output is terminated, and with a form feed. The CP and the edit buffer remain unchanged.

PW output buffer, no form feed

The entire edit buffer is output and no form feed is inserted.

nPW output n lines, no form feed

Starting from the CP, n lines are output, but no form feed. If n is too big, output stops when the end of text in the edit buffer is reached.

The output commands have no effect on the CP or on the buffer contents. In counting the number of lines output, the part of the current line after the CP is counted as the first line.

E output buffer and remaining input

The current contents of the edit buffer plus the remaining input contained in the input device will be output.

R output and read page

One page of the edit buffer is output and the next page is read in. This command is equivalent to writing PY.

nR output and read

The equivalent of a combination of P and Y commands, written n(PY), n pages are output and n pages are read into the edit buffer. OR and 1R are equivalent.

When editing is completed, the output file must then be closed.

GC\$ close output file

will close the output file. This command will not force the output of the last page. This must have been done previously by the execution of a P or an E command.

When using the N command for copying tapes, the execution of the GC command subsequently will have the effect of putting two filemarks at the end of the output tape.

The output file buffer can be emptied only by using the GC or the H command.

H\$ home, restart

The current contents of the edit buffer plus the remaining input contained in the input device or file will be output as for the E command. Additionally the input and output files are closed. After execution the Text Editor is ready for editing another file. H\$\$ is equivalent to E\$GC\$.

2.10 Special Commands

: print number of lines

The number of lines that are in the edit buffer will be displayed.

. CP line number

The number of the line the CP is pointing to will be displayed.

= print number of characters

The number of characters that are in the edit buffer will be displayed.

3 Error Messages

BUFFER CAPACITY EXCEEDED DURING COMMAND INPUT, COMMAND IS TERMINATED	Command string exceeds the capacity of edit buffer.
BUFFER IS FULL - Y OR A INPUT IS TERMINATED	During a read, buffer capacity is exceeded. Part of a page has been read in.
PARITY ERROR IN LINE n	During a read, a parity error occurred in line n. When examined, the character in error will be replaced by a /.
STR NOT FOUND	Unsuccessful string search.
?? COMMAND STRING	Editor cannot understand the command. It displays the command it cannot understand plus the commands that follow it in the command string.
NO SUCH FILE	File name does not exist.
NO INPUT FILE	Input file has not been declared.
ENTRY ALREADY EXISTS	Output file name is in use.
NO OUTPUT FILE	Output file has not been declared.
WRONG FILE NUMBER	Fileno = 0 on magnetic tape or cassette tape during a GR or a GW command.
MACRO CONTAINS X IN COMMAND	The macro is recursive.
MACRO UNDEFINED	No macro has been declared, or the macro has been improperly defined.
device name ERROR error number CORRECT ERROR WRITE STOP/START	A device error has occurred. Consult Operator's Guide for error number.

4 Reference List of MUSIL Text Editor Commands

Command	Format	Meaning	Page
A	A	Append a page	13
B	B	Place CP at beginning of edit buffer	13
C	Cstring ₁ \$string ₂ \$	Search for string ₁ and replace it with string ₂ (also used for string deletions)	16
D	nD	Delete n characters	17
E	E	Output buffer and remainder of input	23
F	F	Output a form feed	22
	nF	Output n inches of leader	22
GC	GC	Close output file	23
GI	GI\$FDn\$	Initialize flexible disc number n. n = 0,1	11
GR	GRinputfilename\$	Get for reading	10
GW	GWoutputfilename\$	Get for writing	10
H	H	Home, restart	23
↑H	CTRL H	Delete last character of the current command ...	8
I	Istring\$	Insert string	16
J	nJ	Jump CP to line n	13
K	nK	Delete n lines	17
L	L	Move CP to beginning of current line	13
	nL	Move CP n lines from current position	14
M	nM	Move CP n character positions	14
N	Nstring\$	Search for string, if necessary through input and output result	18
P	P	Output edit buffer plus form feed	22
	nP	Output n lines plus form feed	22
PW	PW	Output edit buffer	22
	nPW	Output n lines	22
Q	Qstring\$	Search for string, if necessary through input ...	17
R	R	Output edit buffer and read in next page	23
	nR	Output n pages and read in n pages	23
S	Sstring\$	Search for string	17
T	T	Display contents of edit buffer	13
	nT	Display n lines of edit buffer	13
X	X	Execute macro	20
	nX	Execute macro n times	20
XD	XD	Delete macro	20
XM	(see page 20)	Create macro	20
Y	Y	Read a page	12
Z	Z	Place CP at end of edit buffer	14
=	=	Display number of characters in edit buffer	24
:	:	Display number of lines in edit buffer	23
.	.	Display current line number	24

APPENDIX
Disc Cartridge Editor System

Disc Cartridge Editor System

For those who wish to edit MUSIL source language programs to and/or from disc cartridge, a few special commands are provided in addition to the Text Editor commands already described.

Initialization

In addition to the Text Editor commands to be found in the section Device Handling, the Disc Cartridge user must initialize the disc he will use. Initializing a disc consists of creating or updating the disc catalog. If the user wishes to employ an empty disc, or to erase what had previously been written on the disc to be used, the command

GIDISC\$ get disc initialization and erase

will create a new catalog on the disc and erase whatever data had previously been written on it. This new catalog will be mirrored in core.

To use a disc without erasing previous information on it, use

GINIT\$ get disc initialization

which will read the present catalog on the disc into core and prepare the disc for use.

Once the disc has been made ready for use by one of the two above commands, the user might want to remove one of the files from the disc. In this case one writes

GKfilename\$ remove disc file

The keying of this command removes the named file from the disc and from its catalog. The filename must be at most 5 ASCII characters long, and the characters must have ASCII value greater than 32₁₀.

If the RC 3600 system has more than one disc drive, then the system will always assume that the 'first' disc drive, DK0, is meant, unless the user specifies some other disc drive. To do this, write :n before the escape key, thus:

GKfilename:n\$\$

which will inform the system that drive n is meant. The same convention can be used with any disc file command.

For Similar Input and Output Filenames

Once the disc is initialized, the normal "get" and other Text Editor commands may be used. These commands, however, require that the input and output filenames are different from one another, while the programmer may want to use the same filename for the original and the corrected versions, say, of a MUSIL program he is editing.

If the programmer wants the input and output filenames to be the same, then he may not use the GR, GW, and GC commands and may not use Y or E in the normal way. Instead, he must use the following commands:

UYfilename

is the equivalent of

GRinputfilename

Y

GWoutputfilename

The UY command opens the input file and creates an output filename consisting of the input filename with the first character of that filename replaced by a dot. The command then reads in a page of the input file, following the procedure for Y. The filename may have up to five characters. For example, if the input filename is FILE1, then UY will create an output filename

.ILE1

After the UY command has once been used, the Y command can be used to get next pages. But the Y command cannot be used to get the first page.

UE

is the equivalent of

E

GC

GKinputfilename

rename outputfilename to inputfilename

It is used after editing on the file is completed. UE outputs the current contents of the edit buffer plus the remaining input as for the procedure for E. When the output is completed for the file and the output filename is constructed by replacing the "dot name" with the input filename, UE closes both the input and output files, and it removes the original input file.

Before the UE command is used, the E command may be used to get the CP to the end of the file, so that the programmer can write something there. But the E command cannot close the files.

Example of Disc Cartridge Text Editor Commands

GIDISC\$\$	Initialize the first disc, erasing previous data.
GINIT:1\$\$	Initialize the disc unit 1 without erasing previous data.
GKTEST2:1\$\$	Remove the file called TEST2 from the disc unit 1.
GRTEST:1\$\$	Open (for reading) the file called TEST on the disc unit 1.
GWTEST2\$\$	Open (for writing) the file called TEST2 on the disc unit 0.
Y\$\$	Read a page (from the disc unit 1).

Disc Cartridge Error Messages

CATALOG IS FULL	No room for more catalog entries.
CATALOG ERROR	Catalog trouble or disc not connected.
DISC CORE IS FULL	No room for more data on the disc.
NAME TOO LONG	Filename has more than five characters.
ILLEGAL FILENAME	Using the UYfilename\$\$ on a device other than the cartridge disc.
FILE NOT INITIATED WITH UY	Using the UE command without having used a UY command previously.
FILE INITIATED WITH UY-USE-UE-TO-CLOSE FILES	File was initialized with a UY command, but not terminated with a UE command. Make a UE command.

There is room for over 1000 file entries in the disc's catalog.

To interpret error messages containing error numbers, consult the appropriate disc system documentation. In doing so, note that

ERROR 33 driver not loaded

when occurring during a GW command to the cartridge disc means that the filename is already being used by another file on the disc.

The user should remember that when discs are used the catalog processor and the catalog handler must be loaded, in addition to the device drivers and the editor program itself. As stated in the Disc System Programmer's Guide, the catalog processor, CATP, must be loaded before the catalog handler, CAT01.

The load sequence is, therefore,

Interpreter
Device drivers as needed
DP0
DP1 if needed
CATP
CAT01
Text Editor

Note that disc cartridge filenames do not begin with a dollar sign. The reason for this is that the dollar sign is used to distinguish between drivers in core and files on a disc cartridge.

A/S Regnecentralen maintains a continuous effort to improve the quality and usefulness of its publications. To do this effectively we need user feedback - your critical evaluation of this manual.

Please comment on this manual's completeness, accuracy, organization, usability, and readability:

Do you find errors in this manual? If so, specify by page.

How can this manual be improved?

Other comments?

Please state your position: _____

Name: _____ Organization: _____

Address: _____ Department: _____

_____ Date: _____

Thank you!

----- Fold here -----

----- Do not tear - Fold here and staple -----

Affix
postage
here

A/S REGNECENTRALEN
Marketing Department
Falkoner Allé 1
2000 Copenhagen F
Denmark

.....
Cut along the dotted line



INTERNATIONAL

EASTERN EUROPE

A/S REGNECENTRALEN
Glostrup, Denmark, (02) 96 53 66

SUBSIDIARIES

AUSTRIA

RC – SCANIPS COMPUTER
HANDELSGESELLSCHAFT mbH
Vienna, (0222) 36 21 41

FINLAND

OY RC – SCANIPS AB
Helsinki, (90) 31 64 00

HOLLAND

REGNECENTRALEN (NEDERLAND) B.V.
Rotterdam, (010) 21 62 44

NORWAY

A/S RC – SCANIPS
Oslo, (02) 35 75 80

SWEDEN

RC – SCANIPS AB
Stockholm, (08) 34 91 55

SWITZERLAND

RC – SCANIPS (SCHWEIZ) AG
Basel, (061) 22 90 71

UNITED KINGDOM

REGNECENTRALEN LTD.
London, (01) 439 9346

WEST GERMANY

RC – GIER ELECTRONICS G.m.b.H.
Hannover, (0511) 6 79 71

REPRESENTATIVES

FRANCE

SORED S.a.r.l.
Nanterre, (1) 204 2800

HUNGARY

HUNGAGENT AG
Budapest, 88 61 80

TECHNICAL ADVISORY REPRESENTATIVES

POLAND

ZETO
Wroclaw, 45 431

RUMANIA

I.I.R.U.C.
Bucharest, 33 21 57

HUNGARY

NOTO-OSZV
Budapest, 66 84 11

 **A/S REGNECENTRALEN**

HEADQUARTERS: FALKONER ALLE 1; DK-2000 COPENHAGEN F · DENMARK
Phone: (01) 10 53 66 · Telex: 16282 rc hq dk · Cables: regnecentralen